

## 5.Pedometer

### 1. Learning goals

In this lesson, we will learn to use micro:bit and Wrist:bit make a pedometer.

### 2.Code and analysis

```
Pedometer.py x
1 from microbit import *
2 import microbit
3 display.show(Image.HAPPY)
4 step = 0
5 x1 = accelerometer.get_y()
6
7 while True:
8     x2 = accelerometer.get_y()
9     if x2 - x1 > 150:
10         step = step + 1
11     x1 = x2
12     microbit.sleep(500)
13     if button_a.is_pressed():
14         display.scroll(str(step))
15
```

**from microbit import \***


This code is to import everything from the microbit library, and any program need to uses import this library.

**import music:** Import music library.

**acceleromete.get\_y():** Measures the acceleration of the y axis. It will generates a corresponding positive or negative integer according to the direction be changed.

**button\_a.is\_pressed():** When button A on the micro:bit is pressed, it returns True, otherwise it returns False. **button\_b.is\_pressed()** is the same.

**display.scroll():** Scrolls horizontally on the dot matrix. If the value is an integer or a floating-point number, the integer need to be converted to a string.



According to the wear of the watch, the direction of the Y axis is mainly affected by the movement of the arm, so the number of steps is calculated by testing the acceleration change of the Y axis.


**Note:**

- 1 - The capital letter/lowercase letters must be distinguished !
- 2 - Correct spelling!
- 3 - Keywords such as # need a space between the content.
- 4 - You can only use the Tab key (tabulation key) for indentation.


### 3. Programming and downloading

3.1 You should open the Mu software, and enter the code in the edit window, , as shown in figure .


**Note!** All English and symbols should be entered in English, and the last line must be a space.



3.2 As shown in Figure, you need to click the Check button to check if our code has an error. If a line appears with a cursor or an underscore, the program indicating this line is wrong.



3.3 You need to connect the micro data cable to micro:bit and the computer, then click the Flash button to download the program to micro:bit.



#### 4. Experimental phenomena

After the program is successfully downloaded.

Micro:bit dot matrix will display smile pattern, wear it while walking or swinging the arm, press the button A will display the current latest steps.